browser is then directed to a webpage that displays data from the client device 112 or the HUD server 118 (or other server devices).

[0046] In exemplary embodiments, the client data module 308 is configured to receive communication data variables from the communication data module 206 of the HUD server 118. The client data module 308 may receive the communication data variables from the HUD server 118 immediately when the communication data variables become available to the HUD server 118. For example, an inbound phone call to the PBX server 116 will trigger the PBX server 116 to provide communication data variables to the communication data module 206 of the HUD server 118. The communication data variables may then be immediately forwarded to the client data module 308. Substantially simultaneously, the PBX server 116 may route the inbound phone call to the client device 112 or another communication device associated with the same individual. In some embodiments, the receipt of the communication data variables may trigger a review of the browser launch settings to determine when, where, and what type of browser page to launch. In alternative embodiments, other notifications of inbound communication may trigger the review (e.g., receipt of inbound communication from the communication server).

[0047] In embodiments where the client device 112 initiates an outbound communication, the client data module 308 may be configured to detect the communication data variable(s) for the outbound communication. For example, an individual associated with the client device 112 may initiate a phone call to an external user at the external user device 124. Based on the phone number, the client data module 308 may detect corresponding communication data variables such as customer name and account number. In some embodiments, external user data may be locally stored in the client database 310 (e.g., Outlook contacts data). For example, a contacts table may be maintained in the client database 310 which includes communication data variables (e.g., phone numbers, e-mails, name, and addresses) for frequently contacted external users.

[0048] The client database 310 may further store the browser launch settings. The browser launch settings may include, for example, instructions as to when to launch a browser (e.g., before or at the beginning of a communication, during a communication, upon completion of the communication, or any combination thereof), display options, and URL used to obtain data for the browser. An example of a browser launch settings interface is shown and described in more detail in connection with FIG. 4b.

[0049] The browser module 312 is configured to launch a browser. In some embodiments, the browser module 312 may receive launch instructions from the client data module 308 at a predetermined time. The browser may be directed to a specific webpage or be directed to a webpage containing a window or frame directed to a URL that is constructed based on, or otherwise is associated with, one or more of the communication data variables. In some embodiments, the browser is directed to internal information via an internal URL. In these embodiments, the browser module 312 may communicate with the data exchange module 210 to access internal (e.g., within the enterprise central location 102) servers and databases, such as the CRM server 122. In other embodiments, the browser is directed to external information (e.g., information accessed via the network 106) via an external URL. In these embodiments, the browser module 312 may access the network 106 to construct a page containing the external information. For example, an external URL to Google.com may be constructed from one or more communication data variables applied to a Google URL (e.g., Google.com%%callerID_number will provide a Google search of the caller ID number). In other embodiments, the URL may "call" a remote server in the background passing it variables. In this embodiment, the call may be hidden to the individual and the communication with the remote server may be background/covert.

[0050] The exemplary communication module 314 is configured to initiate a communication. In some embodiments, the communication module 314 may send a communication request comprising a contact identifier to the HUD server 118 or other communication server to initiate an outbound communication. For example, a communication request may be forwarded to the HUD server 118 and the communication initiation module 214 may then instruct the PBX server 116 to establish a phone call. In other embodiments, the communication module 314 may send instructions to a local module of the client device 112 to initiate the outbound communication. For example, the communication module 314 may instruct an e-mail module of the client device 112 to provide a new e-mail composition window. The communication module 314 may also receive and establish an inbound communication.

[0051] Referring now to FIG. 4a, an example of a user interface 400 configured to provide event driven browser launch is shown. The exemplary user interface 400 displays individuals within the enterprise and their availability, various communication types available, and the present individual's status. In the present example, the user (i.e., individual using the user interface 400) is identified by name and extension in a top, left display section 402. Local and remote individuals of the enterprise are displayed in a lower portion of the user interface 400, and may be identified by name and extension within a display block 404. The local and remote individuals may be organized in any manner, such as by first name, last name, extension number, team (e.g., sales teams, executive team) or group, and so forth.

[0052] Within each block 404, a plurality of icons 406 may be provided to indicate availability and provide single-click communication functionality. The icons 406 may comprise, for example, an e-mail icon, a cellular/mobile phone icon, phone icon, voicemail icon, and a chat icon. In some embodiments, the user may initiate a phone call or a direct-to-voicemail by clicking on an extension number within the block 404 or by clicking on the individual's name within the block 404. Status of the local and remote individuals may also be received from the HUD server 118 and displayed in each block 404.

[0053] The user interface 400 may also provide access to the browser launch setting interface. In one embodiment, the individual may customize interface settings via selecting a file menu 408 and choosing a HUD setting option. Upon selecting the HUD setting option, a HUD settings interface 410 as shown in FIG. 4b may be displayed. The HUD settings interface 410 allows the individual to customize settings for various functions.

[0054] In the present embodiment, a URL launcher button 412 has been selected which provides a URL launcher settings window 414. The exemplary URL launcher settings window 414 may provide data access options 416 which indicate when the browser should be launched and provides